

AD A 092377
TECHNICAL
LIBRARY

AD

TECHNICAL REPORT ARBRL-TR-02266

WNDWBX: TEKTRONIX PLOTTING ON CDC

Ronald D. Anderson

September 1980



US ARMY ARMAMENT RESEARCH AND DEVELOPMENT COMMAND
BALLISTIC RESEARCH LABORATORY
ABERDEEN PROVING GROUND, MARYLAND

Approved for public release; distribution unlimited.

Destroy this report when it is no longer needed.
Do not return it to the originator.

Secondary distribution of this report by originating
or sponsoring activity is prohibited.

Additional copies of this report may be obtained
from the National Technical Information Service,
U.S. Department of Commerce, Springfield, Virginia
22151.

The findings in this report are not to be construed as
an official Department of the Army position, unless
so designated by other authorized documents.

*The use of trade names or manufacturers' names in this report
does not constitute indorsement of any commercial product.*

REPORT DOCUMENTATION PAGE		READ INSTRUCTIONS BEFORE COMPLETING FORM
1. REPORT NUMBER TECHNICAL REPORT ARBRL-TR-02266	2. GOVT ACCESSION NO.	3. RECIPIENT'S CATALOG NUMBER
4. TITLE (and Subtitle) WNDWBX: TEKTRONIX PLOTTING ON CDC		5. TYPE OF REPORT & PERIOD COVERED BRL Technical Report
7. AUTHOR(s) Ronald D. Anderson		6. PERFORMING ORG. REPORT NUMBER
9. PERFORMING ORGANIZATION NAME AND ADDRESS U.S.A. Armament Research and Development Command U.S.A. Ballistic Research Laboratory ATTN: DRDAR-BLP Aberdeen Proving Ground, MD 21005		8. CONTRACT OR GRANT NUMBER(s)
11. CONTROLLING OFFICE NAME AND ADDRESS U.S.A. Armament Research and Development Command U.S.A. Ballistic Research Laboratory ATTN: DRDAR-BL Aberdeen Proving Ground, MD 21005		10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS 1L161102AH43
14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office)		12. REPORT DATE Sep 80
		13. NUMBER OF PAGES 28
		15. SECURITY CLASS. (of this report) UNCLASSIFIED
		15a. DECLASSIFICATION/DOWNGRADING SCHEDULE
16. DISTRIBUTION STATEMENT (of this Report) Approved for public release; distribution unlimited		
17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report)		
18. SUPPLEMENTARY NOTES		
19. KEY WORDS (Continue on reverse side if necessary and identify by block number) Plot Interactive Tektronix WNDWBX <i>computer graphics</i>		
20. ABSTRACT (Continue on reverse side if necessary and identify by block number) (c1t) WNDWBX is an interactive plotting program accessible through a single Fortran CALL. It uses given input data to generate curves and label axes. Titles, new axis dimensions, and curve labels can be supplied interactively. The user is not required to have plot software knowledge or experience.		

TABLE OF CONTENTS

	Page
LIST OF ILLUSTRATIONS	5
I. INTRODUCTION	7
II. DESCRIPTION	7
III. SAMPLE CASE	8
IV. SUMMARY	14
APPENDIX	21
DISTRIBUTION LIST	23

LIST OF ILLUSTRATIONS

Figure	Page
1. Option Table in Test Plot Routine	9
2. First Plot Using Default Values From Test Routine	10
3. Option Table for Figure 2	11
4. Option 5,6,7, and 8 Exercised From Figure 3	12
5. Test Curves with Titles	13
6. Changing Curve Parameters in Generating Routine	15
7. New Curves using Parameters from Figure 6	16
8. Horizontal and Vertical Axis Parameters Changed to Provide "Zoom" Feature	17
9. "Zoom" Window Using Axis Parameters from Figure 8	18
10. Option 4 Exercised - Return to Original Axis Parameters (Same as Figure 7)	19

I. INTRODUCTION

Due to increasing use of computer models and data manipulation by scientists, there has arisen a need for a plotting package which can show data curves on a computer terminal CRT, yet does not require the casual user to develop his own plotting software. Such a program is available for the Tektronix CRT's on the BRL CDC system.

II. DESCRIPTION

WNDWBX is a Fortran subroutine which uses the Tektronix PLOT10¹ software to generate point-to-point plotting of data vectors. Axes are initially scaled and labeled with parameters returned from the BRL FIXSCA subroutine.²

The user must supply data from some generating program; then through a single Fortran calling statement he can access the plotting routines. The required call is:

CALL WNDWBX (X, Y, M, N, NPTS),

where X = horizontal axis data vector,

Y = vertical axis data vector,

M = maximum number of data points to be plotted,

N = number of curves to be shown on the plotted surface (1 to 3),

NPTS = vector of size (3) containing respective number of data points in each curve. ($M \geq \text{Total of NPTS.}$)

The data-generating main program must define files PLB and KBI in its program statement (see test program listing in the Appendix). WNDWBX requires that the main program be supplied in relocatable form; this may be accomplished in one of two ways:

- A. (1) Attach a source-code file.
- (2) Compile the source code into LGO.
- (3) Attach the WNDWBX procedure.
- (4) Begin the WNDWBX procedure.

As an example, suppose file FORT (ID = FRED and CY = 1) contains the source code in the Appendix. Then,

¹TEKTRONIX Plotting (PLOT10) Package, BRL SPB-8-78, 14 July 1978.

²Monte W. Coleman and John V. Lanahan, "BRLESC Fortran Plotting Subroutines", ARDC Technical Report No. 6, p. 36, July 1970.

Step 1: ATTACH, FORT, ID = FRED, CY = 1.
 Step 2: FTN (I = FORT, L = 0, B = LGO).
 Step 3: ATTACH, WNDWBX.
 Step 4: BEGIN, RUN, WNDWBX, LF = LGO.

or,

B. (1) Attach the WNDWBX procedure.
 (2) Begin the procedure and provide to it a pre-compiled and catalogued main program.

For example, suppose after Step 2 of the previous case that the user decided to catalog his compiled code into file FORT, ID = FRED, CY = 2. (The command would have been: 'CATALOG, LGO, FORT, ID = FRED, CY = 2'.) Then a 'RETURN, LGO' would free the file. Next,

Step 1: ATTACH, WNDWBX.
 Step 2: BEGIN, RUN, WNDWBX, PF = FORT, ID = FRED, CY = 2.

Both methods use a Cyber Control Language procedure to connect I/O files, attach libraries, load and execute the program, and return local files after execution. (Method A uses a copy of LGO to generate an executable program.)

The first time WNDWBX is called, it polls the user for a data transmission rate - either 30, 120, or 960 characters/second (corresponding to 300, 1200, and 9600 baud, respectively). The internal calls to the PLOT10 setup routines assume a screen size of 1024 by 780 addressable points; buffer size is arbitrarily set to 3. These parameters are reasonable in most cases and the user cannot change them.

III. SAMPLE CASE

A simple sine, cosine, and sine + cosine data-generating program is available for test use simply by attaching the WNDWBX procedure and executing the command: 'BEGIN, TEST, WNDWBX'.

The sample case first asks for an input from the user in order to start the data generation. Then a list of options will appear as in Figure 1. If option 1 is chosen (enter the number "1" through the keyboard), an unlabeled set of curves will be shown (Figure 2).

When the curves are shown, there is no screen prompt to tell the user what to do next. Entering any number from the keyboard will cause the graph to disappear and a list of options will appear (Figure 3). Axis and curve titles may be entered through options 5, 6, 7, and 8 (Figure 4). Then option 1 will show the plot with the new titles (Figure 5).

CURVE GENERATING ROUTINE

OPTIONS: 0 = STOP
 1 = PLOT
 2 = CHANGE DATA

OPTION? >1

Figure 1. Option Table in Test Plot Routine




Figure 2. First Plot Using Default Values From Test Routine

```

OPTIONS:
0 = RETURN TO CALLING PROGRAM
1 = PLOT
2 = CHANGE HORIZONTAL AXIS PARAMETERS
3 = CHANGE VERTICAL AXIS PARAMETERS
4 = REVERT TO ORIGINAL AXIS PARAMETERS
5 = CHANGE TITLE *
6 = CHANGE HORIZONTAL AXIS TITLE *
7 = CHANGE VERTICAL AXIS TITLE *
8 = CHANGE CURVE TITLE(S) 1 * 2 * 3 *

                                MIN      MAX      DEL
                                0.      6.00     1.00
                                -1.60   1.60     .400
                                *
                                * *
                                * * *
                                * * *

OPTION? >

```

Figure 3. Option Table for Figure 2

```

OPTIONS:
0 = RETURN TO CALLING PROGRAM
1 = PLOT
2 = CHANGE HORIZONTAL AXIS PARAMETERS
3 = CHANGE VERTICAL AXIS PARAMETERS
4 = REVERT TO ORIGINAL AXIS PARAMETERS
5 = CHANGE TITLE *THIS IS WHERE OVERHEAD TITLE IS PLOTTED *
6 = CHANGE HORIZONTAL AXIS TITLE * HORIZONTAL TITLE *
7 = CHANGE VERTICAL AXIS TITLE * VERTICAL TITLE *
8 = CHANGE CURVE TITLE(S)
                                1 * SINE *
                                2 * COSINE *
                                3 * SIN + COS *

                                MIN      MAX      DEL
                                0.      6.00    1.00
                                -1.60    1.60    .400

```

OPTION? >

Figure 4. Option 5,6,7, and 8 Exercised From Figure 3




Figure 5. Test Curves with Titles

After entering another number to clear the screen, and choosing option 0 to return to the main program, the test case will allow the user to change the curves by entering different coefficients for the equations (Figure 6). The new data is plotted in Figure 7, showing the scientific notation style of axis labeling - three significant figures along the vertical axis and an exponent near the upper left hand corner. WNDWBX uses this style when the axis labels need to show more than three digits. The horizontal axis, too, has this option and the exponent is printed just below the lower left hand corner of the box.

Options 2 and 3 from the option table allow the user to choose a "window" from the original plot by setting new axis maximums and minimums. Figure 8 shows the option table and a new set of axis limits. The plot option at this time gives the graph shown in Figure 9. The intersection of the curves is now visible in much greater detail.

Option 4 returns the axis limits to show the whole curve at the time of the last WNDWBX call (Figure 10).

When using this set of plotting routines, an added feature is available to the programmer - a Fortran-callable screen erasure. A simple CALL ERS at the appropriate step in the generating routine will enable the user to clear the Tektronix screen. Comparing the interactive operation of the test plot program to its Fortran listing in the Appendix will show the value of this subroutine.

IV. SUMMARY

The WNDWBX routine is a powerful tool in modeling applications. It can plot one to three data curves without prior knowledge of the data limits. WNDWBX allows the scientist to inspect the data closely by using the "zoom" feature to select and enlarge any portion of the plotted data. The routines are available and easily used by means of a Cyber Control Language procedure which enters much of the command run-stream for the user.

```

CURVE GENERATING ROUTINE

OPTIONS:  0 = STOP
          1 = PLOT
          2 = CHANGE DATA

OPTION? >2

CURVE 1 = C1 * SIN(X)
CURVE 2 = C2 * COS(X)
CURVE 3 = C3 * ( C1 * SIN(X) + C2 * COS(X) )

NUMBER OF CURVES TO PLOT? >3

MULTIPLIER(S)

COEFFICIENT FOR SIN CURVE? >1000

COEFFICIENT FOR COS CURVE? >2000

COEFFICIENT FOR SIN + COS CURVE? >.5

```

Figure 6. Changing Curve Parameters in Generating Routine




Figure 7. New Curves using Parameters from Figure 6

```

OPTIONS:
0 = RETURN TO CALLING PROGRAM
1 = PLOT
2 = CHANGE HORIZONTAL AXIS PARAMETERS      MIN      MAX      DEL
                                           1.00    1.25    .500E-01
3 = CHANGE VERTICAL AXIS PARAMETERS      850.    950.    10.0
4 = REVERT TO ORIGINAL AXIS PARAMETERS
5 = CHANGE TITLE *THIS IS WHERE OVERHEAD TITLE IS PLOTTED *
6 = CHANGE HORIZONTAL AXIS TITLE * HORIZONTAL TITLE *
7 = CHANGE VERTICAL AXIS TITLE * VERTICAL TITLE *
8 = CHANGE CURVE TITLE(S)      1 * SINE *
                                2 * COSINE *
                                3 * SIN + COS *

```

OPTION? >

Figure 8. Horizontal and Vertical Axis Parameters Changed to Provide "Zoom" Feature




Figure 9. "Zoom" Window Using Axis Parameters from Figure 8




Figure 10. Option 4 Exercised - Return to Original Axis Parameters (Same as Figure 7)

APPENDIX

TEST PROGRAM LISTING

PROGRAM ONE	73/173 OPT=1 ROUND=+-*/	FTN 4.2+498	05/12/80 10.01.17
1	PROGRAM ONE(INPUT,OUTPUT,TAPE9=INPUT,PLH,KB1)		000100
	DIMENSION X(1000),Y(1000),NPTS(3),C1(3),S(3)		000110
	DATA NPTS,C1/300,300,300,3*1.0/		000120
	DATA S/9M SIN ,9M COS ,9H51N + COS/		000130
5	CALL ERS		000140
	PRINT *,'		000150
	PRINT *,' TEST PLOT PROGRAM'		000160
	PRINT *,'		000170
	PRINT *,' ENTER NUMBER TO BEGIN>'		000180
10	READ (9,10) I		000190
	10 FORMAT(11)		000200
	N=3		000210
	GO TO 45		000220
20	CALL EPS		000230
15	PRINT *,'		000240
	PRINT *,' CURVE GENERATING ROUTINE'		000250
	PRINT *,'		000260
	PRINT *,' OPTIONS: 0 = STOP'		000270
	PRINT *,' 1 = PLOT'		000280
20	PRINT *,' 2 = CHANGE DATA'		000290
	PRINT *,'		000300
15	PRINT *,' OPTION? >'		000310
	READ *,IOPT		000320
	IF (IOPT.FQ.0) GO TO 99		000330
25	IF (IOPT.FQ.1) CALL WNOB(X,Y,1000,N,NPTS)		000340
	IF (IOPT.FQ.2) GO TO 30		000350
	IF (IOPT.LT.3.AND.IOPT.GT.0) GO TO 20		000360
	PRINT *,' ERROR.... OPTION UNACCEPTABLE.. PLEASE RE-ENTER>'		000370
	GO TO 15		000380
30	PRINT *,' CURVE 1 = C1 * SIN(X)'		000390
	PRINT *,' CURVE 2 = C2 * COS(X)'		000400
	PRINT *,' CURVE 3 = C3 * (C1 * SIN(X) + C2 * COS(X))'		000410
	PRINT *,'		000420
35	PRINT *,' NUMBER OF CURVES TO PLOT? >'		000430
	READ *,N		000440
	PRINT *,'		000450
	PRINT *,' MULTIPLIER(S)'		000460
	DO 21 I=1,N		000470
	PRINT 40,5(1)		000480
40	40 FORMAT(/' COEFFICIENT FOR ',A9,' CURVE? >')		000490
	READ *,P		000500
	C1(I)=P		000510
	21 CONTINUE		000520
45	40 22 I=1,300		000530
	XX=FLOAT(I-1)*.02		000540
	X(1)=XX		000550
	X(300+1)=XX		000560
	X(600+1)=XX		000570
	Y(1)=C1(1)*SIN(XX)		000580
50	Y(300+1)=C1(2)*COS(XX)		000590
	Y(600+1)=C1(3)*(Y(1)+Y(300+1))		000600
	22 CONTINUE		000610
	GO TO 20		000620
55	99 STOP		000630
	END		000640

DISTRIBUTION LIST

<u>No. of Copies</u>	<u>Organization</u>	<u>No. of Copies</u>	<u>Organization</u>
12	Commander Defense Technical Info Center ATTN: DDC-DDA Cameron Station Alexandria, VA 22314	1	Commander US Army Armament Materiel Readiness Command ATTN: DRSAR-LEP-L, Tech Lib Rock Island, IL 61299
1	Director Defense Advanced Research Projects Agency ATTN: LTC C. Buck 1400 Wilson Boulevard Arlington, VA 22209	1	Director US Army ARRADCOM Benet Weapons Laboratory ATTN: DRDAR-LCB-TL Watervliet, NY 12189
2	Director Institute for Defense Analyses ATTN: H. Wolfhard R. T. Oliver 400 Army-Navy Drive Arlington, VA 22202	1	Commander US Army Watervliet Arsenal ATTN: SARWV-RD, R. Thierry Watervliet, NY 12189
1	Commander US Army Materiel Development and Readiness Command ATTN: DRCMDM-ST 5001 Eisenhower Avenue Alexandria, VA 22333	1	Commander US Army Aviation Research and Development Command ATTN: DRSAR-E P. O. Box 209 St. Louis, MO 63166
2	Commander US Army Armament Research and Development Command ATTN: DRDAR-TSS Dover, NJ 07801	1	Director US Army Air Mobility Research and Development Laboratory Ames Research Center Moffett Field, CA 94035
4	Commander US Army Armament Research and Development Command ATTN: DRDAR-LCA, J. Lannon DRDAR-LC, T. Vladimiroff DRDAR-SCA, L. Stiefel DRDAR-LCE, R.F. Walker Dover, NJ 07801	1	Commander US Army Communications Rsch and Development Command ATTN: DRDCO-PPA-SA Fort Monmouth, NJ 07703
		1	Commander US Army Electronics Research and Development Command Technical Support Activity ATTN: DELSD-L Fort Monmouth, NJ 07703

DISTRIBUTION LIST

<u>No. of Copies</u>	<u>Organization</u>	<u>No. of Copies</u>	<u>Organization</u>
1	Commander US Army Missile Command ATTN: DRSMI-R Redstone Arsenal, AL 35809	1	Director US Army TRADOC Systems Analysis Activity ATTN: ATAA-SL, Tech Lib White Sands Missile Range NM 88002
1	Commander US Army Missile Command ATTN: DRSMI-YDL Redstone Arsenal, AL 35809	2	Office of Naval Research ATTN: Code 473 G. Neece 800 N. Quincy Street Arlington, VA 22217
1	Commander US Army Natick Research and Development Command ATTN: DRXRE, D. Sieling Natick, MA 01762	1	Commander Naval Sea Systems Command ATTN: J. W. Murrin, SEA-62R2 National Center Bldg. 2, Rm 6E08 Washington, DC 20362
1	Commander US Army Tank Automotive Research & Development Cmd ATTN: DRDTA-UL Warren, MI 48090	1	Commander Naval Surface Weapons Center ATTN: Library Br, DX-21 Dahlgren, VA 22448
1	Commander US Army White Sands Missile Range ATTN: STEWS-VT White Sands, NM 88002	2	Commander Naval Surface Weapons Center ATTN: S.J. Jacobs, Code 240 Code 730 Silver Spring, MD 20910
1	Commander US Army Materials and Mechanics Research Center ATTN: DRXMR-ATL Watertown, MA 02172	1	Commander Naval Underwater Sys Center Energy Conversion Department ATTN: R. S. Lazar, Code 5B331 Newport, RI 02840
3	Commander US Army Research Office ATTN: Tech Lib D. Squire F. Schmiedeshaff R. Ghirardelli M. Ciftan P. O. Box 12211 Research Triangle Park NC 27706	2	Commander Naval Weapons Center ATTN: R. Derr C. Thelen China Lake, CA 93555

DISTRIBUTION LIST

<u>No. of Copies</u>	<u>Organization</u>	<u>No. of Copies</u>	<u>Organization</u>
1	Commander Naval Research Laboratory ATTN: Code 6180 Washington, DC 20375	1	Atlantic Research Corporation ATTN: M. K. King 5390 Cherokee Avenue Alexandria, VA 22314
3	Superintendent Naval Postgraduate School ATTN: Tech Lib D. Netzer A. Fuhs Monterey, CA 93940	1	AVCO Corporation AVCO Everett Research Lab Div ATTN: D. Stickler 2385 Revere Beach Parkway Everett, MA 02149
2	Commander Naval Ordnance Station ATTN: A. Roberts Tech Lib Indian Head, MD 20640	1	Foster Miller Associates, Inc. ATTN: A. J. Erickson 135 Second Avenue Waltham, MA 02154
3	AFOSR (B.T. Wolfson; D. Ball; L. Caveny) Bolling AFB, DC 20332	1	General Electric Company Armament Department ATTN: M. J. Bulman Lakeside Avenue Burlington, VT 05402
2	AFRPL (DYSC, D. George; J.N. Levine) Edwards AFB, CA 93523	1	General Electric Company Flight Propulsion Division ATTN: Tech Lib Cincinnati, OH 45215
2	National Bureau of Standards ATTN: J. Hastie T. Kashiwagi Washington, DC 20234	2	Hercules Incorporated Alleghany Ballistic Lab ATTN: R. Miller Tech Lib Cumberland, MD 21501
1	Lockheed Palo Alto Rsch Labs ATTN: Tech Info Ctr 3521 Hanover Street Palo Alto, CA 94304	1	Hercules Incorporated Bacchus Works ATTN: B. Isom Magna, UT 84044
1	Aerojet Solid Propulsion Co. ATTN: P. Micheli Sacramento, CA 95813	1	IITRI ATTN: M. J. Klein 10 West 35th Street Chicago, IL 60615
1	ARO Incorporated ATTN: N. Dougherty Arnold AFS, TN 37389		

DISTRIBUTION LIST

<u>No. of</u> <u>Copies</u>	<u>Organization</u>	<u>No. of</u> <u>Copies</u>	<u>Organization</u>
1	Olin Corporation Badger Army Ammunition Plant ATTN: J. Ramnarace Baraboo, WI 53913	1	Shock Hydrodynamics, Inc. ATTN: W. H. Anderson 4710-16 Vineland Avenue North Hollywood, CA 91602
2	Olin Corporation New Haven Plant ATTN: R. L. Cook D. W. Riefler 275 Winchester Avenue New Haven, CT 06504	1	Thiokol Corporation Elkton Division ATTN: E. Sutton Elkton, MD 21921
1	Paul Gough Associates, Inc. ATTN: P. S. Gough P. O. Box 1614 Portsmouth, NH 03801	3	Thiokol Corporation Huntsville Division ATTN: D. Flanigan R. Glick Tech Lib Huntsville, AL 35807
1	Physics International Company 2700 Merced Street Leandro, CA 94577	2	Thiokol Corporation Wasatch Division ATTN: J. Peterson Tech Lib P. O. Box 524 Brigham City, UT 84302
1	Pulsepower Systems, Inc. ATTN: L. C. Elmore 815 American Street San Carlos, CA 94070	1	TRW Systems Group ATTN: H. Korman One Space Park Redondo Beach, CA 90278
3	Rockwell International Corp Rocketdyne Division ATTN: C. Obert J. E. Flanagan A. Axeworthy 6633 Canoga Avenue Canoga Park, CA 91304	2	United Technologies Chemical Systems Division ATTN: R. Brown Tech Lib P. O. Box 358 Sunnyvale, CA 94086
2	Rockwell International Corp Rocketdyne Division ATTN: W. Haymes Tech Lib McGregor, TX 76657	1	Universal Propulsion Co. ATTN: H. J. McSpadden 1800 W. Deer Valley Rd. Phoenix, AZ 85027
1	Science Applications, Inc. ATTN: R. B. Edelman Combustion Dynamics & Propulsion Division 23146 Cumorah Crest Woodland Hills, CA 91364	11	Battelle Memorial Institute ATTN: Tech Lib R. Bartlett (10 cys) 505 King Avenue Columbus, OH 43201

DISTRIBUTION LIST

<u>No. of</u> <u>Copies</u>	<u>Organization</u>	<u>No. of</u> <u>Copies</u>	<u>Organization</u>
1	Brigham Young University Dept of Chemical Engineering ATTN: M. W. Beckstead Provo, UT 84601	1	Pennsylvania State University Dept of Mechanical Engineering ATTN: K. Kuo University Park, PA 16801
1	California Inst of Tech 204 Karmar Lab Mail Stop 301-46 ATTN: F. E. C. Culick 1201 E. California Street Pasadena, CA 91125	1	Pennsylvania State University Dept of Material Sciences ATTN: H. Palmer University Park, PA 16801
1	Case Western Reserve Univ Division of Aerospace Sciences ATTN: J. Tien Cleveland, OH 44135	1	Princeton Combustion Rsch Lab ATTN: M. Summerfield 1041 U.S. Highway North Princeton, NJ 08540
3	Georgia Institute of Tech School of Aerospace Eng ATTN: B. T. Zinn E. Price W.C. Strahle Atlanta, GA 30332	2	Princeton University Forrestal Campus ATTN: I. Glassman Tech Lib P. O. Box 710 Princeton, NJ 08540
1	Institute of Gas Technology ATTN: D. Gidaspow 3424 S. State Street Chicago, IL 60616	2	Purdue University School of Mech Engineering ATTN: J. Osborn S.N.B. Murthy TSPC Chaffee Hall W. Lafayette, IN 47906
1	Johns Hopkins University/APL Chemical Propulsion Info Agency ATTN: T. Christian Johns Hopkins Road Laurel, MD 20810	1	Rutgers State University Dept of Mechanical and Aerospace Engineering ATTN: S. Temkin University Heights Campus New Brunswick, NJ 08903
1	Massachusetts Inst of Tech Dept of Mechanical Engineering ATTN: T. Toong Cambridge, MA 02139	4	SRI International ATTN: Tech Lib D. Crosley J. Barker D. Golden 333 Ravenswood Avenue Menlo Park, CA 94025
1	Pennsylvania State University Applied Research Lab ATTN: G. M. Faeth P. O. Box 30 State College, PA 16801		

DISTRIBUTION LIST

<u>No. of Copies</u>	<u>Organization</u>
1	Stevens Institute of Technology Davidson Library ATTN: R. McAlevy, III Hoboken, NJ 07030
1	University of California, San Diego Ames Department ATTN: F. Williams P.O. Box 109 La Jolla, CA 92037
1	University of Illinois Dept of Aeronautical Engineering ATTN: H. Krier Transportation Bldg, Rm 105 Urbana, IL 61801
1	University of Minnesota Dept of Mechanical Engineering ATTN: E. Fletcher Minneapolis, MN 55455
1	University of Southern California Dept of Chemistry ATTN: S. Benson Los Angeles, CA 90007
	University of Texas Dept of Chemistry W. Gardiner H. Schaefer Austin, TX 78712
	University of Utah Dept of Chemical Engineering A. Baer G. Flandro Salt Lake City, UT 84112
	<u>Proving Ground</u> ISAMSAA 1: DRXSY-D DRXSY-MP, H. Cohen ISATECOM 1: DRSTE-TO-F ISACSL, Bldg. E3516 1: DRDAR-CLB-PA

USER EVALUATION OF REPORT

Please take a few minutes to answer the questions below; tear out this sheet and return it to Director, US Army Ballistic Research Laboratory, ARRADCOM, ATTN: DRDAR-TSB, Aberdeen Proving Ground, Maryland 21005. Your comments will provide us with information for improving future reports.

1. BRL Report Number _____
2. Does this report satisfy a need? (Comment on purpose, related project, or other area of interest for which report will be used.)

3. How, specifically, is the report being used? (Information source, design data or procedure, management procedure, source of ideas, etc.) _____

4. Has the information in this report led to any quantitative savings as far as man-hours/contract dollars saved, operating costs avoided, efficiencies achieved, etc.? If so, please elaborate.

5. General Comments (Indicate what you think should be changed to make this report and future reports of this type more responsive to your needs, more usable, improve readability, etc.) _____

6. If you would like to be contacted by the personnel who prepared this report to raise specific questions or discuss the topic, please fill in the following information.

Name: _____

Telephone Number: _____

Organization Address: _____

